2025/06/21 02:18 1/3 Installation

Installation

Requirements

- Universal Fighting Engine (PRO or Source)
- Understanding of U.F.E tools
- Unity 4.5 or higher
- Know your way around the basic tools and terminology from Unity

Package

If acquired from Unity's Asset Store:

- Go to Window > Asset Store > Downloaded Assets
- Select Fuzzy AI for UFE and click on the Import/Update button.

If acquired from other stores:

- Double click the unitypackage file or
- Go to Main Menu > Assets > Import Package > Custom Package
- Browse to the location of the downloaded unitypackage and open it.

Starting Fuzzy Al

If you decide to start a new scene, skip to *Starting a new scene*. As soon as you import Fuzzy Al onto UFE you will be able to see the following new options:

- Under Global Editor, Al Options -> Al Engine: Fuzzy Al
- Under Character Editor, Al Instructions
- Under Move Editor, Al Definitions
- New Editor: A.I. Editor (under Window → U.F.E.)


Notes:

- Global Editor -> Al Options will now have Fuzzy Al options enabled. Use it to create different
 difficulty settings. If you are using the UFE_Config.asset file that comes with UFE, you
 should now see 3 new predefined difficulty settings already assigned by default.
- Before being able to see it in action you need to assign a few instruction files to your characters. Each of the demo characters should now appear with 3 empty A.I. Instruction slots each.
- Feel free to choose any of the fighting templates from the folder UFE Addons\AI Addon\Templates. This is my recommendation:

Last update: 2014/10/26 16:53

- Mike: Mix-up set (Mixup Aggressive, Mixup Balanced, Mixup Defensive)
- Robot Kype: Rush down set (RushDown_Aggressive, RushDown_Balanced, RushDown_Defensive)
- Mecanim Bot | Joan: Rush down set (RushDown_Aggressive, RushDown_Balanced, RushDown Defensive)

Recommended Layout:



Updates

When updating UFE to a new version, if you don't want to move your work to a new project, you can follow these procedures:

Remember to always backup projects before importing a new update!

- Close Unity.
- Replace the files under .\UFE Addons\AI Addon\Runtime\ and .\UFE Addons\AI Addon\Editor\ with the files from the new version of Fuzzy Al.
- Open Unity.

< Back to Universal Fighting Engine - Fuzzy Al

From:

http://www.ufe3d.com/ - Universal Fighting Engine

Permanent link:

http://www.ufe3d.com/doku.php/ai:installation?rev=1414356783

Last update: 2014/10/26 16:53



http://www.ufe3d.com/ Printed on 2025/06/21 02:18

2025/06/21 02:18 3/3 Installation