# **Predefined Rules**

Here you can toggle and adjust a few general instructions for the Al. This process automatically generates its own fuzzy rules.



### **Movement**

**Auto Move:** Toggle to make the Al move on its own until it reaches its desired position.

**Rest On Location:** If toggled, the character will try to remain still when it reaches its destination.

**Preferable Distance:** The destination to which the character will want to move to. The further they are from the target, the higher is the desirability to move.

**Move Frequency:** On a scale from 0 to 6 (in correlation with the desirability options), how much priority should the AI decide to move.

# **Jump**

**Auto Jump:** Toggle to make the Al jump on occasions. If *Auto Move* is toggled on, the Al decision to

Last update: 2014/10/15 04:52

jump may be affected by the preferable distance chosen.

Jump Back Frequency: How often should the AI jump back.

**Jump Straight Frequency:** How often should the AI jump straight (this decision is not affected by preferable distance).

**Jump Forward Frequency:** How often should the Al jump forward.

#### **Attack**

**Auto Attack:** Toggle to make the Al attempt to play moves. If *Auto Move* is toggled on, the Al decision to attack may be affected by the preferable distance chosen.

**Use Range Filters:** When enabled, the AI will prioritize moves with range that match the distance they are in. Example: If you have a fireball with A.I. Definitions  $\rightarrow$  Range: Far, the AI will prioritize that move over others if they are far from the opponent.

**Attack Frequency:** How often should the AI attempt to play a move.

## **Block**

**Auto Block:** Toggle to make the AI attempt to block moves. Blocking will be attempted as soon as the opponent begins executing a move, and will end as soon as it begin the *recovery frames*.

**Use Hit Type Filters:** If enabled, the AI will attempt to read A.I. Definitions  $\rightarrow$  Hit Type from the opponent's move to determine if they should block high or low. If this option is toggled off the AI will attempt high or low based solo on the frequency set below.

**Stand Block Accuracy/Frequency:** How often should the Al attempt to block standing.

**Crouch Block Accuracy/Frequency:** How often should the AI attempt to block low attacks.

**Jump Block Frequency:** How often should the AI attempt to block while jumping.

For more about Predefined Rules and the Rule Generator used, consult the following script: Script: .\UFE Addons\Runtime\AIRulesGenerator.cs

< Back to A.I. Editor

http://www.ufe3d.com/ Printed on 2024/05/09 16:26

From:

http://www.ufe3d.com/ - Universal Fighting Engine

Permanent link:

http://www.ufe3d.com/doku.php/ai:predefinedrules?rev=1413363145

Last update: 2014/10/15 04:52

