

## Requirement

- Some knowledge of fighting game terminologies and overall understanding of how it works (hit boxes, active frames, hit stun etc.)
  - Unity 2018.2 or higher
  - **Basic understanding of Unity:**
    - Know your way around the basic tools (project, inspector, hierarchy, scene view)
    - Terminologies
    - How to use [prefabs](#)
    - How to handle your own 3D models and animations
    - For more information and full documentation please visit [ufe3d.com](#)
    - For more on Unity, visit [unity3d.com](#)
- 

## Package

### If acquired from Unity's Asset Store:

- Go to Window > Asset Store > Downloaded Assets
  - Select UFE 2 and click on the Import/Update button.
- 

## Project Settings

Upon installation UFE will attempt to automatically update the Input Manager under Project Settings. If this fails, you might end up with a few errors such as controls not working or characters falling off the screen. A common description of this error can be found in the Unity's error console as *"UnityException: Input Axis (..) is not setup"*. To fix this error and update your Input Manager settings follow these steps:

- Close Unity.
  - Using the explorer and navigate to (Project Folder)\Assets\UFE\ProjectSettings
  - Open ProjectSettings.zip
  - Extract its content to (Project Folder)\ProjectSettings
  - Reopen your project in Unity
- 

## Getting Started

### Opening the demo files:


- Navigate to UFE\Demo\ and double click TrainingRoom.unity. Hit play to start the Demo.



- To open the global config file for the demo, click on UFE\Demo\Config.asset and under the inspector, click to open the [Global Editor](#).
- To view a [Character](#) file, navigate to UFE\Demo\Characters\[Character]\[Character].asset or, under the [Global Editor](#), select [Characters](#).
- To open a [Move](#) file, unfold the [Move Set option](#) under the [Character Editor](#) or navigate to .\UFE\Characters\[Character]\Moves\[Move].asset.
- You can also open any of the editors from the top toolbar under Window → U.F.E..
- To create a new UFE file, under the Project Tab, click Create→UFE and select the file of your choice.

### Starting a new scene:

- Click File > New Scene
- Make sure you have a camera on scene (Hierarchy view).
- Create a new Game Object, click Add component and add both Event System and UFE.
- Drag your [Global Config](#) file under UFE\_Config, make sure you have your characters and moves setup and hit play.



## Updates

To update an existing copy of your UFE follow [these instructions](#).

[< Back to Universal Fighting Engine - Introduction](#)

From:

<http://www.ufe3d.com/> - **Universal Fighting Engine**

Permanent link:

<http://www.ufe3d.com/doku.php/installation?rev=1533808996>

Last update: **2018/08/09 06:03**

